



NotePad 1.4

Copyright 2006, miniMusic

Table of Contents

Installing Software	3
NotePad	4
Library Screen	5
Score Screen	5
Piano Screen	6
Grid Screen	7
Page Screen	7
Editing (Selecting, Menus, Changes)	8
Graffiti/Keyboard	9
Working with Voices	10
Preferences	11
Krikit Audio Engine	12
Utilities (miniAlarm & NotePad Conduit)	13
Using MIDI	14
FAQ & Troubleshooting	15
Sample Song Library	16
End User License	17

www.miniMusic.com

Visit our website for further help, frequently asked questions, and other resources for making music on your handheld computer. Also feel free to e-mail your questions or comments to us at support@minimusic.com

INSTALLING SOFTWARE

IMPORTANT NOTES BEFORE INSTALLATION

- Before installing NotePad on your handheld computer or smart-phone, please read the license found at the end of this manual. INSTALLING THE SOFTWARE SIGNIFIES YOUR ACCEPTANCE OF THIS LICENSE.
- The NotePad application can be installed on any handheld computer or smart-phone that uses the Palm OS (version 3.0 or higher).

INSTALLING NOTEPAD ON YOUR HANDHELD

Inside the NotePad folder (or on the NotePad CD-ROM) there is the NotePad application “NotePad.prc” and a sample song library named “mMusicDB.pdb”. The “NotePad.prc” file is the one you will install on your handheld computer or phone. We recommend that you also install the “mMusicDB.pdb” file, but it is optional (if the sample library is not installed NotePad will create an empty one to store your songs).

If you have an earlier version of NotePad already installed, this .prc file will replace the older one. If you have existing NotePad songs do not install the “mMusicDB.pdb” file; it will replace your existing songs (the sample songs are primarily the same as were included with older versions of the software, so you should already have them).

Consult the documentation that came with your handheld to learn how to install new software.

SONY CLIE USERS

If your Sony Clie has a “High Res Support” feature, please turn it off for NotePad. You will find this option by running the Prefs application that came pre-installed on your Clie. Choose “High Res Support” from the pop-up menu in the top right corner of the Prefs screen and find NotePad in the list of applications.

WINDOWS CONDUIT INSTALLATION

You can download a free HotSync conduit for Windows from our website at this address:

<http://www.minimusic.com/conduit.html>

The conduit will export songs you write in NotePad to your desktop or laptop computer as a standard MIDI file that can be used in other music software, audio players or posted on websites. After you download, double click the “NotePadConduit.EXE” file; this will automatically install the MiniMusic.dll file on your computer in the proper place and check that you have the necessary versions of other HotSync files. This installer expects that you have already installed the Palm Desktop software that is included with all PalmOS handhelds. The next time you do a HotSync the conduit will run automatically and export MIDI files for all of the songs written with NotePad. The files will be located in a new “miniMusic” folder created by the conduit.

MACINTOSH CONDUIT INSTALLATION

We do not have a Mac OSX version of our conduit; we recommend Mac OSX users instead take advantage of the “Export Song” feature built into NotePad that will create MIDI files on your handheld’s removable memory card.

You can download a free HotSync conduit for classic Mac operating systems from our website at this address:

<http://www.minimusic.com/conduit.html>

To install the conduit on a Macintosh, simply find the “Conduits” folder inside the “Palm” folder on your hard drive. These folders were created when you installed the Palm Desktop software that was included with your handheld (if you haven’t installed that software yet, do it now!). Copy the NotePadConduit.PPC file into the “Conduits” folder. The next time you do a HotSync the conduit will run automatically and export MIDI files for all of the songs written with NotePad. The files will be located in a new “NotePad Songs” folder created by the conduit.

MINIMUSIC NOTEPAD

With NotePad you use standard music notation to enter music into your PalmOS handheld, edit it, and play it back. NotePad also lets you enter music using an on-screen piano keyboard, write in notes using Palm's Graffiti handwriting recognition technology, type them on a keyboard, draw notes onto a grid (like a player piano roll) or even play songs on an attached electronic musical instrument (See 'MIDI' section on page 14 for more about that).

Most handhelds today are capable of running our Krikit Audio Engine which is built into NotePad. This "software synthesizer" can generate complex music with chords and different instrument sounds. Most older handhelds are only capable of monophonic playback, meaning they can only play one pitch at a time (no chords or counterpoint). You can also export songs as standard MIDI files to use in other music software on your desktop or laptop computer, or use them on a website.

SAVING SONGS

NotePad saves songs as you work on them, so you don't need to take any action to save your work. When you open NotePad everything will be just as you left it. If you want to save the current state of a song before making changes, you should copy and paste the voices from the original song into a new song.


THE LIBRARY SCREEN

When you first open NotePad you will see the **Library** screen (the NotePad Demo opens in the **Score** screen, described below). This screen lists all of your songs. If you did not install the sample library, the list will be empty and your only choice will be to create a new song by tapping the “New” button in the bottom left corner.

If the songs will not fit on the screen, up and down scroll arrows will appear in the lower right corner. The size of each song (in bytes or kilobytes) is listed on the right side of the screen. To play or edit a song, tap on the name of a song. To write a new song, tap the “New” button.


In the top right corner is the category. The “All” category lists every song starting with the most recent. Tap on the word “All” to change to a more specific category.

From the Library screen you can get to any of the three edit screens. At the bottom of the Library screen there are three boxes that say “Score”, “Grid”, and “Piano”. You can select any one of these as your **Launch Screen**, the first screen you want to see when you tap on the name of a song. You can always switch to another screen after the song is opened by tapping on the Screen Icons in the lower right corner of each edit screen.



THE SCORE SCREEN

In the **Score** screen, the grand staff is the main feature. In the top left corner is the name of the current song. To the right of the name are the note durations you can choose from: whole note, half note, quarter note, eighth note, and sixteenth note. To the right of these is the “Rest” toggle (the little squiggly line). Tap this to highlight or un-highlight it; when selected you can write rests of the same duration as the selected note duration (if only the quarter note is highlighted you can write quarter notes; if both the rest tool and quarter note are highlighted you can write quarter rests). In the very top right corner is the voice indicator (see “Working with Voices” on page 10).



To add a note, select the desired duration from the top of the screen (a quarter note, for example) and then tap on the staff where you would like that note. Notes will automatically sort themselves by duration: if you tap in an empty area, the note will be added in the first available position to the left; if you tap between two existing notes, the notes to the right will be pushed over to make room. Longer note durations will take up more space on the screen making it easier to see the relative lengths of notes, see the proper number of notes in each measure, and align beats in all voices. To write dotted or tied durations see the Editing section.

Notes will sometimes be pushed to the right and into the next measure. You can move between measures with the **Scroll Arrows** at the bottom of the screen (immediately to either side of the measure number which appears near the center of the screen).

When placing a note, it will be drawn the moment the stylus touches the screen. While the stylus is still down you can drag the note; you can change the pitch by dragging it up or down, or you can move it back and forth through the measure and the existing notes will jump out of the way automatically to make room.

If you place a note directly on top of another note, a chord will be created. The new note's duration will be changed to match the duration of the note that was already there. Sometimes it is hard to tap the stylus directly onto those tiny notes, so it is often easier to place a new note after (to the right of) where you want to make a chord and, while the stylus is still touching the screen, gently drag the new note to the left until it creates a chord with the previous note. If you drag too fast or too far the notes might simply change places instead of creating a chord. After a couple practice chords this will become very easy to do.

When you lift the stylus, the new note has been successfully placed. A small arrow (red arrow on color screens) above the staff will indicate where a note was most recently added. This little arrow will always indicate the current **Selected Note**, or the beginning of a selection that may include many notes (see 'Editing' on page 8).


When you tap the Play button in any of the three edit screens, the song will play from the beginning and the Play button will become a Stop button. However, a tap anywhere on the screen will stop the playback. Until playback stops, all buttons (including the power button) will be temporarily disabled in order to prevent the Palm OS from interrupting playback. No Palm alarms or low battery warnings will occur during playback. When playing songs in the "Basic Sound" mode only the current voice will be played, and only the top note of any chords will be played. All other playback modes will play all four voices and chords. See the Preferences section on page 10 for more about these playback modes.

THE PIANO SCREEN

In the **Piano** screen, there is a condensed staff (like in the Score screen) and a piano keyboard underneath it. The staff in this view is small enough that you can now see three measures on screen, but to fit it all there are no accidentals or ties shown, the key signature is printed next to the tempo, but not shown on the staff. Also, you cannot enter notes directly on the staff as you can in the Score screen (it's too small to tap the right pitch!); instead, any tap on the staff will select notes.


To add notes in the Piano screen, select the desired duration from the top tool bar, tap the score overview where you want the new note to be added, and play the note you want on the piano keyboard. The new note will appear immediately after the **Selection Pointer** (the little arrow above the staff). If there is no Selection Pointer new notes will appear at the beginning of the song.

Tapping the keyboard will play a note as long as the stylus is down. However, the new note will only be added when you lift the stylus and it will be of the duration selected at the top of the screen regardless of how long you hold the stylus on the piano keyboard. If you tap on the wrong piano key, simply drag the stylus to the correct key and then lift the stylus. You can also play freely on the keyboard by un-checking the "Notate" checkbox just above the keyboard; notes will only be added to the song when it is checked. Two octaves are available to play on-screen; use the arrows on either side of the keyboard to access the lower and higher octaves (each 'C' key will be marked with the number of the octave you are in: 1-4. The 'C' labeled with a 3 is "Middle C").



THE GRID SCREEN

In the **Grid** screen you can write music in a graphic format with time running side to side (bars are divided by solid lines; beats are divided by dotted lines) and pitch running up and down.



The tool bar at the top of the screen has the same Page icon, Arrow tool and Voice Indicator as you saw in the Score screen, plus a Pencil tool and Eraser tool. With the Pencil tool chosen, tapping on the screen will add a new note. It will start as a sixteenth note. While you hold the stylus down, you can change the pitch of the new note by dragging up or down. You can also stretch the note to the right for a longer duration. The note will automatically “write over” any existing notes and rests as you stretch it. Since it is writing over existing material, you cannot un-stretch it. Notes in different voices will be drawn in different patterns; if you have a color display the voices will be drawn in different colors. The Eraser tool clears notes in a similar fashion (It is actually “drawing” a rest, but this is not visible in the Grid screen; if you switch to the Score or Piano screens you will see the rests).


After a note is drawn, you can still change its length (this is true in all three edit screens) by simply entering the space and backspace characters (using Graffiti or a keyboard).

Only three of the four usable octaves fit on the screen vertically. To see or draw notes in the lowest or highest octaves, use the up/down octave arrows above and below the piano keyboard along the left side of the screen. The small piano keyboard is here only as a reference and will not play when you tap on it.

THE PAGE SCREEN

From any of the editing screens you can “zoom out” to the **Page** screen by tapping on the page icon, or type or write the letter ‘z’. In the Page screen you can view 20 measures of music at a time. The measure you just came from (the left-most measure in the Piano or Grid screens) is highlighted. You can scroll a page at a time and then tap on a measure to zoom in on it.

You cannot currently enter notes, edit notes, or play the song from the page screen; you must first switch to one of the other three edit screens.



EDITING

SELECTING NOTES

When you add a note to a song a small arrow will appear directly above the new note (selected notes are red on color handhelds, except in the Grid screen). This is the **Selection Pointer**, and means that the note is 'selected' and is ready to be edited (so you can easily clear a wrong note or correct its pitch or duration immediately after it is added).

To select a different note, or several notes, choose the "Arrow" tool (beneath the bass clef in the Score screen, or in the top tool bar of the Grid screen), then tap on a note to select it. In the Piano screen, any tap will select a note.

To select several notes, tap on the first note (the arrow will appear) and drag the stylus to the right until an "open" arrow appears above the last note you want selected. You cannot select a note that is tied over from a previous measure; you must first move back to the previous measure and then select it. While selecting a range of notes, you can drag the pen to the right edge of the screen to advance to the next measure. If you scroll too far you can drag the stylus to the left edge of the screen to scroll back.

Options Menu

Get Info – Displays information about the NotePad software (e.g. version number).

Help – Shows a short version of these instructions.

Preferences – Shows the song/application preferences screen (see Preferences section on page 11).

Krikit Settings – Displays the settings for the built-in synthesizer.

Beam Song – Sends a copy of the song to another handheld (both handhelds must have NotePad installed).

Export Song – Creates a MIDI file version of the song on a removable memory card (SD card or Memory Stick).

Delete Song – Erases the song from the database and returns to the Library screen.

Edit Menu

Cut – Copies selection to the clipboard and removes it from the song.

Copy – Copies selection to the clipboard without removing it from the song.

Paste – Insert contents of the clipboard into the song immediately after the current selection.

Clear – Remove selection from song without changing the clipboard.

Select Voice – Select the entire current voice.

Invert – Flip selection vertically, highest note becomes the lowest, etc. Centered on first note of selection.

Retrograde – Flip the selection horizontally, first note becomes last, etc.

Triplet – Make selected notes into triplets, or make normal if they already are triplets.

Flip Stem – Changes the direction the note stem points on notes that have stems.

Play Menu

Play Song – Play entire song.

Play Section – Play the current selection (will start play from the current measure in some modes).

Loop Section – Repeat the selection until another event occurs (or loop from the current measure to the song's end).

Changes Menu

Change Tempo – Insert a tempo change on the selected note.

Change Instrument – Insert an instrument change on the selected note.

Clear changes – remove any tempo or instrument changes found in the current selection.

Tempo and Instrument changes are assigned to a particular note in a particular voice. To clear a change you must select that note in that voice. It is recommended that you place all tempo changes in voice 1, unless no appropriate note or rest exists in voice 1. Instrument changes for voices 1 & 2 will be shown above the treble clef, changes for voices 3 & 4 will be shown below the bass clef.

GRAFFITI/KEYBOARD

Rather than fill the small screen with lots of tool bars and tabs and options to be selected or toggled, NotePad takes advantage of Graffiti handwriting recognition or the keyboards built into some handhelds and phones. Most editing and navigation can be accomplished with a simple button press or pen stroke.

Note Entry

“a-g” Adds a note of that pitch.

“A-G” (capitol) Adds a sharp note of that pitch.

“r” Adds a rest.

Editing

“x” Clear selected note or notes.

“up/down” Transposes notes up or down by half-step.

“+/-” Transposes selected notes up/down by octave.

“space” Increase duration of selected note or notes.

“backspace” Decrease duration of selected note or notes.

“t” Convert selected notes to triplet durations, or the reverse if they already are triplets.

Playback

“p” Play the song from the beginning.

“s” Play the current selection (will start play from the current measure in some modes).

“o” Repeat the selection until another event occurs (or loop from the current measure to the song’s end).

Navigation

“q” Close the song, switch to the Library screen.

“z” Zoom out to the page view.

“left/right” Move forward back by measure or page.

Voice


“v” Show/hide the other voices (i.e. show only the current voice, or show all four voices together).

“1-4” Switch to that voice number.

Tools

“y” Choose the previous duration tool.

“u” Choose the next duration tool.



WORKING WITH VOICES

You can write four simultaneous voices in a song, numbered 1–4. These voices are used to write counterpoint (two or more different melodic lines playing together) or parts for different instruments. Most modern handheld computers are able to run our Kriket Audio Engine (or Kriket Synth) which is built into NotePad. The Kriket Synth lets you hear all four voices played together; on older handhelds (Palm OS 4 or earlier) you will only be able to hear the current voice played, unless your handheld has a sound card or is connected to MIDI hardware.

In the upper right corner of any of the three edit screens is a little box with a number in it (it is set to “1” when you start NotePad for the first time); this is the **Voice Indicator**. Tapping on the voice indicator brings up the **Voice Preferences** screen where you can change settings and see what voice you are writing in.

Tap on one of the numbered boxes to make changes to that voice. Instead of bringing up the Voice Preferences screen, you can also change voices by simply writing or typing in the number (1–4) of the desired voice. The current voice will always be shown in the top right corner.



Each voice can have a different name. This is useful when writing music for many instruments. Use the arrows to set a MIDI channel for each voice (1–16). Set the channel to 10 to use a drum kit. Each channel can be set to a different instrument; if two or more voices share a channel they will be played on the same instrument.

Using the slider you can set the MIDI or Kriket Synth instrument for the current voice. Whenever you move the slider the instrument name will change to the general MIDI instrument for that number. Press the “Test” button to hear a sample note played with the current instrument (remember: this will only work when connected to a MIDI instrument). Also, you

can use the checkbox in the lower left corner to mute any particular voice. This will let you listen to a single voice, or a combination of two or three voices.

Voice 1 is intended to be the highest voice and Voice 4 the lowest. You will see these intended positions reflected in the placement of rests and the stem directions of the notes (notes in Voice 1 & 3 will have stems up, Voice 2 & 4 stems down).

When “Show 4 Voices” is checked in the Preferences screen (see next section: “Preferences”), all four voices will be drawn on screen. When it is unchecked, only the **Current Voice** will be drawn (the Current Voice number is the one shown in the top right corner). You can toggle between them by writing a Graffiti “v”. New notes will be added to the Current Voice.



Adding a note to Voice 3

PREFERENCES


The top half of the screen contains preferences for the current song (like its name, category and key signature) while the bottom half of the screen contains application wide preferences (like volume and playback options). The application preferences will remain the same from song to song. Get to the Preferences screen by tapping on the tempo marking in any edit screen or choose “Preferences” from the Options menu. A new song will be set by default to the key of C-Major (a-minor), 4/4 time, and a tempo of 120 beats per minute.

To name the song in the field at the top of the screen use Graffiti or the pop-up keyboard. Songs will be set to “Untitled” by default but it is okay to have multiple songs with the same name. The only conflict that may result from several songs having the same name is when you are exporting songs as MIDI files; they must have unique names or one will overwrite the other.

You may place songs into different categories, just as you would in the Palm’s built-in applications (like Date Book and Memo Pad). Choose the category here for this song, or create a new category.

A key signature can be set for each song. This will only be drawn in the Score screen (and written in the Piano View), but will affect notes entered when using Graffiti in all three views. If you are in the Piano screen and in the key of B-flat. When you write a Graffiti “b” a B-flat will be added to the song, because it is in the song’s key, but since you are in the Piano screen no accidentals will be shown.

The third pop-up menu will let you choose a time signature for the song. You have your choice of 3/4, 4/4, 5/8, and 7/8. We have restricted it to these values so that you can always see at least one full measure on the screen even when filled with sixteen sixteenth notes. They cover the basic sub-divisions, so you could use the 3/4 setting to write music in 6/8, or the 4/4 setting to write two bars of 4/8. The tempo will always be displayed for the quarter note regardless of the selected time signature.



The last item in the Song preferences section is a tempo slider and indicator. Slide the marker to the right for faster tempos, and to the left for slower tempos. Tap on the arrows to make small changes in the tempo.

The Application preferences section begins with three checkboxes. “Show 4 Voices” will draw material in all four voices on screen simultaneously. When this is un-checked, only the Current Voice will appear (see the previous section “Working with Voices” for more information). “Play On Entry” means that you will hear a pitch played whenever you add a note to a song. You will still hear the song play when this is un-checked, but not when notes are entered. Finally, “MIDI in” will allow you to step record notes played on an attached electronic instrument (see “Using MIDI” on page 13 to learn how to connect your Palm to an electronic music instrument).

The “Play To:” pop-up menu lets you choose how music is played. “Simple Sound” plays only the current voice on the speaker built into your handheld. “Serial Port” will play the song on an attached electronic musical instrument (see the MIDI section for details). “Sound Card” uses the enhanced sound capabilities of some handhelds (The Tapwave Zodiac, The Sony T, TG, NR, NX and NZ series Clies, or a Handspring Visor with the Beat Plus springboard module). The default on most handhelds is “Kriket Synth” which uses our powerful software synthesizer to generate rich audio. See the next section: “Kriket Audio Engine” for more information.

Move the volume slider right to make it louder and left to make it quieter. A value of 127 is the loudest and 0 is silent. This will effect the volume of the built-in speaker or headphones and MIDI playback as well.

KRIKITAUDIO ENGINE

Palm OS 5.0 (“Garnet”) or later is needed to use the Krikit Audio Engine (or “Krikit Synth”). Some handhelds have OS 5 but are missing needed sound libraries (e.g. the Zire 21 or Zire 22). If your OS 5 handheld has a headphone jack it should support the Krikit Synth.

The Krikit Audio Engine is a polyphonic, multi-timbral software synthesizer. That means it can play many different pitches simultaneously and use different instrument sounds. The Krikit Synth uses banks of instrument sounds designed with the miniMusic SoundPad application. Each bank can contain up to 256 different instruments.

When using the Krikit Synth, each of NotePad’s voices can be assigned to a different instrument in the Voice Preferences screen (see “Working with Voices” above). To the right of the instrument number you will see how many oscillators are needed to play that instrument sound (a number from 1-4). The Krikit Synth has a limited number of oscillators available; if they are all being used, a new note will cause an older note to stop.

At the top of the Krikit Settings screen (choose “Krikit Settings” from the Options menu) you can set how many oscillators are available. You can have up to 32 oscillators, but this requires extra processing power. Handhelds with slower CPUs will have to be set at a lower number.


The Sample Rate determines how many digital samples are generated every second. The 44.1 rate gives you higher quality audio, however the 22.05 rate will allow a slower CPU to run more oscillators.

Trying to use more oscillators than your CPU can handle will result in stuttering, broken audio. Reduce the number of oscillators or reduce the sample rate to improve playback.

The Sound Bank pop-up menu will let you access other banks of instrument sounds. The miniMusic SoundPad application will let you edit or create your own sound banks.

With 'Auto-Gain' turned on, the Krikit Synth will automatically lower the master volume during playback to prevent 'clipping'. Clipping occurs when the combined volume of all the sounds being mixed has exceeded the maximum volume available in the digital audio hardware. You can turn auto-gain off to get slightly more volume (but expect some clipping).

With 'Play Octave Up' selected, notes will be played an octave higher than written. This greatly improves playback on the built-in speakers of most handhelds as they cannot play low frequencies well. This setting is less important when using headphones.



MINIALARM & THE NOTEPAD CONDUIT

Two utilities have been included with NotePad. The miniAlarm utility allows you to create Palm alarm sounds out of any song in your NotePad Song Library. The NotePad Conduit will automatically export songs to your desktop computer as standard MIDI files that can be used with almost any music software available for your desktop computer or even posted on the internet (like the music in those greeting cards on-line!).

MINIALARM

The miniAlarm utility (minialarm.prc) can be installed the same way as the NotePad application, and resides on your PalmOS handheld as a separate application. When you open miniAlarm, it resembles the NotePad Library screen. All of your songs are displayed and the same categories are available. However, when you tap on the name of a song, instead of going to one of the Edit Views you are asked if you wish to create a System Alarm out of that song. If you tap OK, an alarm (with the same name as the song) is added to the Alarms on your Palm. These alarms are used by built-in applications like Palm's Date Book, and other third party applications. Alarms must be a single voice, so only Voice 1 will be used from the selected song. If there are chords in Voice 1, only the first pitch written will be used in the alarm.

Some of the handhelds include other clock applications that to different alarms than the Date Book does; we may add support for exporting these alarms or for ringtones in the future. We intend to incorporate miniAlarm entirely into the next version of NotePad so there will no longer be a separate program to install.

NOTE PAD CONDUIT

We are no longer developing the NotePad conduit. Instead we have an "Export Song" feature built into NotePad, found in the Options menu. The conduit will not correctly handle tempo changes and instrument changes within a song, but the Export Song feature will.

If the NotePad conduit was not included in your purchase, you can download it for free from our website at:

www.miniMusic.com/conduit.html

The NotePad Conduit is used by Palm's HotSync Manager to synchronize NotePad with your desktop computer. Whenever you perform a HotSync, Standard MIDI files will be created on your desktop computer for any songs that have been modified since the previous HotSync. The very first time you use the NotePad Conduit every song will be exported.

There are separate versions of the NotePad Conduit for Macintosh OS 9 and Windows desktop computers. Instructions for installation and use are provided at the beginning of this manual (page 2).

MIDI

WHAT IS MIDI?

MIDI (Musical Instrument Digital Interface) is an industry standard for communicating with electronic musical instruments. A computer might communicate with an electronic instrument or one electronic instrument might be communicating with another.

MIDI consists of very simple performance commands. This allows MIDI information to be very fast and stored in very small files making it ideal for the Palm platform. It is also very easy to make changes to MIDI data giving it much more flexibility than a Digital Audio or MP3 file.

CONNECTING YOUR PALM TO A MIDI INSTRUMENT.

Connecting to MIDI hardware requires an "RS232 Serial" connection. This was available on all early handheld computers, but is no longer common. Most handhelds today use USB and ship with USB cradles or cables. Since these handhelds can't act as USB hosts, they can't connect to MIDI hardware using USB. Many handhelds still offer limited support for serial connections (those using Palm's multi-connector, for example) but often is not full RS232 serial and would require additional hardware to bridge to a MIDI device. Future handhelds may be able to act as USB hosts and can then use USB-MIDI interfaces.

Older handhelds (like the Palm m100 or m500 series) can use our MIDI interface designed specifically for the Palm. It converts a Serial HotSync Cradle or Cable into a MIDI-out interface that you can connect to any electronic music instrument. Our interface can be ordered from our website at minimusic.com/interface.html and it is included in our Mobile Software Pack. Some OS 5 handhelds with the "Universal Connector" (like the Tungsten T or Zire 71) can be connected to MIDI hardware either with our interface or with a direct serial connection as described below.

DIRECT SERIAL CONNECTIONS FROM YOUR HANDHELD TO MIDI HARDWARE.

Many MIDI keyboards, sound modules, samplers, and synthesizers allow for "direct" serial connections (different than the usual large round 5-pin MIDI-In and MIDI-Out ports). This direct serial port is a smaller round 8-pin port usually labeled "serial", "host" or "to host" on the MIDI instrument. This additional port is intended for a direct connection to your computer (as opposed to another MIDI device) and will often have a Mac/PC switch next to it.

To connect the bottom of your handheld computer to the "to host" serial port on a MIDI device you will need either the Serial HotSync Cradle that came with your handheld, or the optional Serial HotSync Cable. These HotSync cables/cradles end with a somewhat rectangular 9-pin connector. To make this fit in the round "to host" port you will need the "Macintosh Serial Adapter" available from Palm for about \$5 US.

The "To Host" port will usually have a switch associated with it. This switch should be set to "Mac" (as opposed to "PC-1" or any other option). Consult the manual for your MIDI hardware for any special settings that it may require to receive serial data from a computer. Most electronic music products made in the 90s have the "to host" serial port. Newer products may have a USB port instead which cannot be used to connect to any current handhelds.

USING OTHER MIDI INTERFACES WITH YOUR PALM

With a Serial HotSync cradle/cable as described above, you can plug into a number of older (pre-USB) MIDI adapters made for the Macintosh. We have successfully plugged Palm handhelds into interfaces from Opcode (like the "Professional Plus" 1-in/3-out MIDI adapter) to drive MIDI hardware and our users have reported success with a variety of other Mac interfaces. Such interfaces have the small round serial port and full size round 5-pin MIDI ports to connect to other MIDI hardware.

There are also some small third party MIDI solutions designed specifically for the Palm platform. Several web sites will either sell you handmade interfaces or show you how to build your own.

MIDI HARDWARE FOR THE PALM

General MIDI tone modules for the Palm (like a sound card) were made for some handheld models. The SG20 from Swivel Systems will clip onto the base of Palm III or Palm VII style handhelds. The Tsunami is designed for the Palm V or Vx. For all of you Visor owners there was the Beat Plus Springboard module.

FAQ&TROUBLESHOOTING

HOW DO I MAKE A NOTE SHARP OR FLAT?

In the Piano screen, you simply tap on a black piano key. Although since the notation is drawn so small, you will not see the sharps or flats unless you switch to the Score screen to zoom in on a measure. In the Score screen, new notes will be in the song's key signature (which may include sharp and flat pitches). If you want to place a note outside of the current key, first add a note, then use the up/down directional buttons on your handheld or phone to transpose up/down by half-step. You can also type or write the letter names of notes to add them; to enter a sharp note use a capital letter ('a' adds an A-natural, 'A' adds an A-sharp or B-flat).

HOW DO I MAKE A DOTTED NOTE?

Add a note of the correct pitch and then stretch or shrink the duration by using the "space" and "backspace" characters. You can use Graffiti strokes (simple line from left-to-right or from right-to-left) or keyboard buttons on some handhelds and phones (like the Treo, or the Tungsten C).

HOW DO I DELETE A NOTE?

Type or write the letter "x" to clear any selected note or notes. When you add a note to a song it is automatically selected so that you can immediately clear that note, or alter it with other editing options. You can also choose "Clear" from the Edit menu.

HOW DO I TIE TWO NOTES TOGETHER

To get a tied duration (like a half note tied to a sixteenth) start with a basic duration (like a half note) and then increase or decrease the duration by writing or typing the space or backspace characters.

HOW DO I USE DRUM SOUNDS?

You must set the voice you want to use for drums to play on MIDI channel 10. See the section "Working with Voices" on page 10. When playing on channel 10, every pitch has a different drum sound.

I DON'T HEAR ANY SOUND

If you are using a Treo phone, make sure you haven't set the switch on top to "silent mode". Next you should check that the volume is turned up. You can do this with the wide triangle control found on each edit screen, or at the bottom of the preferences screen (choose "Preferences" from the Options menu). Finally, check the "Play To:" setting found near the center of the Preferences screen. For most handhelds this should be set to "Play To: Krikrit Synth". If it is set to "Play To: Serial Port" you will not hear any sound.

HOW DO I MAKE A 32ND NOTE?

Due primarily to the small screen size NotePad does not currently support 32nd notes. We could display them on some high resolution screens, but they would be too small to tap on and edit. We expect to add 32nd note support in a future version.

HOW DO I IMPORT A MIDI FILE?

MIDI files are designed to handle real-time performances, not notation, so they may contain many events that are not yet supported in NotePad. This means we would have to make fundamental changes to most songs when importing them. We are constantly adding new features to NotePad and expect to offer importing soon.

SAMPLE SONG LIBRARY

CLASSICAL SONG CATEGORY:

Sonata.403 - Mozart: Sonata for Violin and Piano, K. 403 (III)
German - Schubert: German Dance
French #6 - J.S.Bach: French Suite No. 6 BWV 817 (minuet)
Invention - J.S.Bach: Two-Part Invention No. 14 BWV 785 (arranged by C. Mealey)
Sonata - Beethoven: Piano Sonata, Op. 13 (III)
Prelude - Chopin: Prelude, Op. 28, No. 6
Trout - Schubert: "Trout" Quintet, D 667 (IV)
Mazurka - Chopin: Mazurka, Op. Posth. 67, No. 4

FOLK SONG CATEGORY:

Lift Ev'ry - J. R. Johnson & J.W. Johnson: Lift Ev'ry Voice and Sing
Chinese - Peking Opera aria transcribed from the recording, The Ruse of the Empty City
Swedish - "Polska" transcribed by Bruno Nettl
Rumanian - from Walter Wiora, Europaischer Volksgesang
English - from Jan P. Schinhan, ed., The Music of the Ballads
Hungarian - from Zoltan Kodaly, Folk Music of Hungary
Russian - from Elsa Mahler, Altrussische Volkslieder aus dem Pecoryland
Morris - Morris Dance, English

X-MAS CATEGORY:

Angles We - Angles We Have Heard on High (Traditional)
JingleBell - Jingle Bells (James Pierpoint)
The1stNoel - The First Noel (Traditional)
Deck Halls - Deck The Halls (Traditional)
O Xmas Tree - O Christmas Tree (Traditional)
Good King - Good King Wenceslas (Traditional)
SilentNite - Silent Night, Holy Night (Traditional)
Joy2World - Joy To The World (Lowell Mason)
Greensl'vs - What Child is This (Traditional)

UNFILED CATEGORY:

miniDemo - C. Mealey (with quotes from Arthur "Guitar Boogie" Smith and Mykola Dmytrovich Leontovych)

END USER LICENSE AGREEMENT FOR MINIMUSIC NOTEPAD

NOTICE TO USER:

THIS IS A CONTRACT. BY INSTALLING THE SOFTWARE YOU ACCEPT ALL THE TERMS AND CONDITIONS OF THIS AGREEMENT. This miniMusic End User License Agreement accompanies the miniMusic NotePad software, and related explanatory materials ("Software"). The term "Software" also shall include any upgrades, modified versions or updates of the Software licensed to you by miniMusic. Please read this Agreement carefully. Use and/or installation of this software will constitute acceptance of this agreement. If you do not wish to accept this Agreement, return or destroy any and all copies of the Software. Upon your acceptance of this Agreement, miniMusic grants to you a nonexclusive license to use the Software, provided that you agree to the following:

1. Use of the Software. • You may install the Software on a Palm Computing device, or other Palm OS device, and make backup copies of the Software. • You may not make or distribute any copies of the Software, or install copies on other devices (unless owned and operated by you), by electronic, infra-red, or other means, with the exception of the clearly marked demo versions of the Software that specifically identify your right to share copies.

2. Copyright and Trademark Rights. The Software is owned by miniMusic and its suppliers, and its structure, organization and code are the valuable trade secrets of miniMusic and its suppliers. The Software also is protected by United States Copyright Law and International Treaty provisions. You may use trademarks only insofar as required to comply with Section 1 of this Agreement and to identify printed output produced by the Software, in accordance with accepted trademark practice, including identification of trademark owner's name. Such use of any trademark does not give you any rights of ownership in that trademark. Except as stated above, this Agreement does not grant you any intellectual property rights in the Software.

3. Restrictions. You agree not to modify, adapt, translate, reverse engineer, decompile, disassemble or otherwise attempt to discover the source code of the Software. Although you may customize the preferences for the Software, you may not otherwise alter or modify the program or create a new installer for the Software. The Software is licensed and distributed by miniMusic for creating, viewing, and editing music files. Any plug-in or enhancement, unless distributed by miniMusic or its suppliers, may not be used with the Software.

4. No Warranty. The Software is being delivered to you AS IS and miniMusic makes no warranty as to its use or performance. MINIMUSIC AND ITS SUPPLIERS DO NOT AND CANNOT WARRANT THE PERFORMANCE OR RESULTS YOU MAY OBTAIN BY USING THE SOFTWARE OR DOCUMENTATION. MINIMUSIC AND ITS SUPPLIERS MAKE NO WARRANTIES, EXPRESS OR IMPLIED, AS TO NON-INFRINGEMENT OF THIRD PARTY RIGHTS, MERCHANTABILITY, OR FITNESS FOR ANY PARTICULAR PURPOSE. IN NO EVENT WILL MINIMUSIC OR ITS SUPPLIERS BE LIABLE TO YOU FOR ANY CONSEQUENTIAL, INCIDENTAL OR SPECIAL DAMAGES, INCLUDING ANY LOST PROFITS OR LOST SAVINGS, EVEN IF A MINIMUSIC REPRESENTATIVE HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES, OR FOR ANY CLAIM BY ANY THIRD PARTY. Some states or jurisdictions do not allow the exclusion or limitation of incidental, consequential or special damages, or the exclusion of implied warranties or limitations on how long an implied warranty may last, so the above limitations may not apply to you.

5. Governing Law and General Provisions. This Agreement will be governed by the laws of the State of California, U.S.A., excluding the application of its conflicts of law rules. This Agreement will not be governed by the United Nations Convention on Contracts for the International Sale of Goods, the application of which is expressly excluded. If any part of this Agreement is found void and unenforceable, it will not affect the validity of the balance of the Agreement, which shall remain valid and enforceable according to its terms. You agree that the Software will not be shipped, transferred or exported into any country or used in any manner prohibited by the United States Export Administration Act or any other export laws, restrictions or regulations. This Agreement shall automatically terminate upon failure by you to comply with its terms. This Agreement may only be modified in writing signed by an authorized officer of miniMusic. Unpublished-rights reserved under the copyright laws of the United States.

miniMusic, 921 Rivera Street, San Francisco, CA 94121.
miniMusic, miniMusic NotePad, Krikit Synth and SoundPad are trademarks of miniMusic.

YOUR ACCEPTANCE OF THE FOREGOING AGREEMENT IS INDICATED BY INSTALLATION AND USE OF THE SOFTWARE.